

How To Use IB Demo Program

Version 2.0.1 (April 27, 2018)

Copyright ©2011-2018, Integrated Biometrics LLC. All Rights Reserved



Contents

| | |
|--|-----------|
| 1 .SUPPORTED FEATURES | 2 |
| 2. PROGRAM LAYOUT | 3 |
| 2.1 Main View | 4 |
| 2.2 Capture View | 5 |
| 2.3 Option View..... | 6 |
| 3. HOW TO SCAN FINGER | 7 |
| 4. HOW TO SAVE IMAGES | 10 |
| 5. HOW TO ANNOTATE FINGER..... | 12 |
| 6. HOW TO ZOOM IN-OUT | 13 |
| 7. CAPTURE SEQUENCE DESCRIPTION | |

1 .Supported features

| Item | 1.0.0 | Remark |
|-------------------------------|-------|--------|
| Save bmp image | O | |
| Save wsq image | O | |
| Save ISO 19794-4 image | O | |
| NFIQ | O | |
| Image zoom-in out | O | |
| Checking Duplicate | O | |
| Checking Finger position | O | |
| Smear Detection(Add to 09/30) | O | |

2. Specification

| Item | | Specification |
|------------|---------------------------|--|
| Mechanical | Device Dimension | 114mm(W) x 132mm(L) x 72 (H), 4.5"(W) x 5.2"(L) x 2.8"(H) |
| | Device Weight | < 0.6Kg |
| Hardware | Interface | USB 2.0 High speed/Full speed, Plug & Play |
| | Sensor Type | Light Emitting Sensor (LES) |
| | Camera | CMOS Image sensor |
| | Resolution | 500DPI |
| | Image size | Slap 80mm(W) x 76mm(L), 3.2"(W) x 3"(L) |
| | | Roll 40mm(W) x 38mm(L), 1.6"(W) x 1.5"(L) |
| | Indicate | LED Green, Red, Orange |
| | | Buzzer Magnetic Buzzer |
| | Extra Button | Supported two Buttons |
| | Supply Voltage | USB Level 4.40V ~ 5.25V |
| | Operating Current | Max 350mA |
| | Operating Temperature | -10°C ~ 55°C |
| | Humidity | 20 ~ 95 %RH < 40°C, Non-condensing |
| | Water and dust protection | TBD |
| | Static Discharge | IEC61000-4-2 Air Discharge : ±8kV Contact Discharge : ±4kV |
| | Sunlight | Has no effect on fingerprint image |
| | Certifications | TBD |
| Software | FBI Certifications | TBD |
| | API Interface | Capture One finger |
| | | Capture Two finger |
| | | Capture Four finger |
| | | Capture roll image |
| | | BIOAPI 2.0 |
| | Supported OS Driver | Window 2000, Window XP, Window 7, Vista, Linux |


2. Program Layout

2.1 Main View

You can select device

You can select capture sequence

You can save captured images



You can see sequence preview


You can see captured images

Getting Started Guide

2.2 Capture View

You can see finger quality

You can see capture sequence




You can start capture finger

You can return to main view

You can see capture image

Getting Started Guide

2.3 Option View




You can set Pre-Annotation finger

You can select image formats
(bmp, wsq ,iso19794-4)

You can set minimum
acceptable NFIQ (1 ~ 5).


You can set finger
duplication permission

You can set Smear
Detection for roll




3. How to Scan finger


1. Select device and capture sequence you want to scan




2. Select "Capture" button.



3. Click "Scan fingers" button to proceed capture sequence




4. According to finger indicator, put your fingers on the scanner




Getting Started Guide

5. Once you input all fingers, the capture sequence will be finished.




If you want to go back to main view, click "Close" button.

< Main view >



Getting Started Guide

6. If you want to capture specific sequence again, you can click that button.




If you want to capture "Both thumbs" again, you can click "Both thumbs" button and capture again.


Getting Started Guide

4. How to save images

1. If you have finished the capture sequence, you can save the captured images by selecting the “Save” button




< Option menu >




You can select image formats

Getting Started Guide

2. Select folder path to save images




<Saved images >




5. How to annotate finger

1. Annotate fingers using the Option




2. Annotate finger from within the "Capture View" by right clicking the mouse button.



Getting Started Guide

6. How to Zoom In-Out

1. Right Click mouse button on main view image to show zoom in-out window




Right Click mouse button

<zoom in-out window>




Getting Started Guide



2. If you want to see other image, you can select that button.



If you want to see "Thumbs" image, you can click "Thumbs" button





3. Mouse Wheel Up/Down to zoom in or out











Getting Started Guide

4. Left Click and move mouse to navigate the zoomed image







7. Capture sequence description

| Capture sequence name | Layout image | signification |
|---------------------------------|--|---|
| 1 prints(both thumbs) |  | Scan 1 image : Two Flats Finger (Both thumbs) |
| 10 prints (2-2-2-2-2) |  | Scan 3 images : Two Flats Finger(Both thumbs) (Left Four, Right Four and Two Thumbs) - Scan left and right thumbs at the same time |
| 10 prints (2-2-2-2-1-1) |  | Scan 3 images : Two Flats Finger (Left Four, Right Four and Two Thumbs) - Scan left and right thumbs separately |
| 10 prints using one flat finger |  | Scan 10 images: One flat finger |

| Capture sequence name | Layout image | signification |
|---|---|--|
| 10 prints using one rolled finger |  | Scan 10 images: One rolled finger |
| 20 prints (2-2-2-2-2-flats) |  | Scan 14 image: One flat finger 10 images and Two flats finger (Left Four, Right Four and Two Thumbs) - Scan left and right thumbs at the same time |
| 20 prints (2-2-2-2-1-1-rolled) +scan 14 images |  | Scan 14 image: One rolled finger 10 images and Two flats finger (Left Four, Right Four and Two Thumbs) - Scan left and right thumbs separately |
| 20 prints (2-2-2-2-2-rolled) |  | Scan 14 image: One rolled finger 10 images and Two flats finger (Left Four, Right Four and Two Thumbs) - Scan left and right thumbs at the same time |

Getting Started Guide

| Capture sequence name | Layout image | signification |
|--|--|--|
| 2 prints(thumbs) |  | Scan 2 Thumbs (Left, Right thumbs) One flat finger 2 images (Left Thumb and Right Thumb) |
| 4 prints (thumbs + indexes) |  | Scan 4 image (thumbs-indexes) : One flat finger 4 images (Left Thumb, Left Index, Right Thumb and Right Index) |
| 20 prints (2-2-2-2-1-1-rolled) + scan 16 images |  | Scan 16 image: One rolled finger and Two flat finger - Scan left and right thumbs separately |
| 20 prints (2-2-2-2-2-1-1-rolled) |  | Scan 19 image: One rolled finger and Two flats finger - Scan left and right thumbs at the same time after Scan left and right thumbs separately |

Support Contact Information:

www.integratedbiometrics.com

Integrated Biometrics, LLC

North American Office

Physical Address for Package Delivery

121 Broadcast Drive
Spartanburg SC 29303

For Mailings & Correspondence

PO Box 170938
Spartanburg, SC 29301

US & Canada

(864) 990-3711
Toll-free (888) 840-8034
Extension 1 – Company Directory
Extension 2 – Technical Support
Extension 3 – Sales Support
Extension 4 – Marketing
Extension 5 – Accounting
Extension 0 – Main Line

Sales & Pricing Inquiries

sales@integratedbiometrics.com

[Terms & Conditions of a Sale](#)

[Terms & Conditions for Supplier Purchases](#)

Sales Administration

marci.bowers@integratedbiometrics.com

Technical Support

technical@integratedbiometrics.com

South Korean Office

Physical Address and Mailing Address

#910 Suntech-City1, 513-15
Sangdaewon 1-dong Jungwon-gu
Seongnam-si, Gyeonggi-do
Republic of Korea

Phone

+82-31-777-2207

Sales Administration

everun@ibkr.co.kr